# MP4RecordingClass

#### **Description**

A class used to record video and audio data streams into a MP4 file on the SD card.

#### **Syntax**

class MP4Recording

#### **Members**

#### **Public Constructors**

MP4Recording::MP4Recording Constructs a MP4Recording object

#### **Public Methods**

MP4Recording::configVideo Initialize MP4Recording video stream

parameters.

MP4Recording::configAudio Initialize MP4Recording audio stream

parameters.

MP4Recording::begin Start recording MP4 to SD card.

MP4Recording::end Stop recording MP4 to SD card.

MP4Recording::setRecordingFileName Set base file name of recorded MP4 files.

MP4Recording::setRecordingDuration Set per-file MP4 recording duration.

MP4Recording::setRecordingFileCount Set total number of MP4 files to record.

MP4Recording::setLoopRecording Enable loop recording mode for continuous

recording.

MP4Recording::setRecordingDataType	Enable recording video data and audio data.
MP4Recording::getRecordingFileName	Get currently configured base file name of recorded MP4 files.
MP4Recording::getRecordingDuration	Get currently configured per-file MP4 recording duration.
MP4Recording::getRecordingFileCount	Get currently configured total number of MP4 files to record.
MP4Recording::getRecordingState	Get current MP4 recording state.
MP4Recording::printInfo	Print current MP4 recording parameters.

# MP4Recording::configVideo

#### **Description**

Initialize MP4Recording video stream parameters.

#### **Syntax**

void configVideo(VideoSetting& config);

#### **Parameters**

config: VideoSetting class object containing desired video configuration

#### Returns

NA

### **Example Code**

Example: RecordMP4SingleVideoWithAudio

(https://github.com/ambiot/ambpro2\_arduino/blob/dev/Arduino\_package/hardware/libraries/Video/examples/RecordMP4SingleVideoWithAudio/RecordMP4SingleVideoWithAudio.ino)

### **Notes and Warnings**

# MP4Recording::configAudio

#### **Description**

Initialize MP4Recording audio stream parameters.

### **Syntax**

void configAudio(void);

#### **Parameters**

NA

#### Returns

NA

### **Example Code**

 ${\bf Example: Record MP4Single Video With Audio}$ 

(https://github.com/ambiot/ambpro2\_arduino/blob/dev/Arduino\_package/hardware/libraries/Video/examples/RecordMP4SingleVideoWithAudio/RecordMP4SingleVideoWithAudio.ino)

### **Notes and Warnings**

# MP4Recording::begin

## **Description**

Start MP4 recording to SD card.

### **Syntax**

void begin(void);

#### **Parameters**

NA

#### Returns

NΑ

### **Example Code**

 ${\bf Example: Record MP4Single Video With Audio}$ 

(https://github.com/ambiot/ambpro2\_arduino/blob/dev/Arduino\_package/hardware/libraries/Video/examples/RecordMP4SingleVideoWithAudio/RecordMP4SingleVideoWithAudio.ino)

### **Notes and Warnings**

# MP4Recording::end

## **Description**

Stop MP4 recording to SD card.

## **Syntax**

void end(void);

#### **Parameters**

NA

#### **Returns**

NA

## **Example Code**

NA

## **Notes and Warnings**

# MP4Recording::setRecordingFileName

#### **Description**

Set base file name of recorded MP4 files.

#### **Syntax**

void setRecordingFileName(const char\* filename); void setRecordingFileName(String filename);

#### **Parameters**

filename: Desired recorded MP4 filename, expresses as a character array or String class object

#### Returns

NΑ

### **Example Code**

Example: RecordMP4SingleVideoWithAudio

(https://github.com/ambiot/ambpro2\_arduino/blob/dev/Arduino\_package/hardware/libraries/Video/examples/RecordMP4SingleVideoWithAudio/RecordMP4SingleVideoWithAudio.ino)

## **Notes and Warnings**

Filename can be up to 127 characters long.

# MP4Recording::setRecordingDuration

#### **Description**

Set per-file MP4 recording duration.

#### **Syntax**

void setRecordingDuration(uint32\_t secs);

#### **Parameters**

secs: Duration of MP4 to record, expressed in seconds

#### Returns

NA

### **Example Code**

Example: RecordMP4SingleVideoWithAudio

(https://github.com/ambiot/ambpro2\_arduino/blob/dev/Arduino\_package/hardware/libraries/Video/examples/RecordMP4SingleVideoWithAudio/RecordMP4SingleVideoWithAudio.ino)

#### **Notes and Warnings**

# MP4Recording::setRecordingFileCount

#### **Description**

Set total number of MP4 files to record.

#### **Syntax**

void setRecordingFileCount(uint32\_t count);

#### **Parameters**

count: Total number of MP4 files to record to SD card

#### Returns

NΑ

#### **Example Code**

Example: RecordMP4SingleVideoWithAudio

(https://github.com/ambiot/ambpro2\_arduino/blob/dev/Arduino\_package/hardware/lib\_raries/Video/examples/RecordMP4SingleVideoWithAudio/RecordMP4SingleVideoWithAudio.ino)

#### **Notes and Warnings**

If configured to record more than 1 file, a number will be appended to the end of the base file name.

# MP4Recording::setLoopRecording

### **Description**

Enable loop recording mode for continuous recording.

### **Syntax**

void setLoopRecording(int enable);

#### **Parameters**

enable: Enable or disable loop recording

#### **Returns**

NA

### **Example Code**

NA

## **Notes and Warnings**

Enabling loop recording will overwrite the oldest previously recorded MP4 file when the total number of MP4 files to record has been reached.

# MP4Recording::setRecordingDataType

#### **Description**

Enable recording video data and audio data.

#### **Syntax**

void setRecordingDataType(uint8\_t type);

#### **Parameters**

type: one of the following values, default value of STORAGE\_ALL
STORAGE\_ALL – record both video data and audio data
STORAGE\_VIDEO – record only video data
STORAGE\_AUDIO – record only audio data

#### Returns

NΑ

#### **Example Code**

Example: RecordMP4VideoOnly

(https://github.com/ambiot/ambpro2\_arduino/blob/dev/Arduino\_package/hardware/libraries/Video/examples/RecordMP4VideoOnly/RecordMP4VideoOnly.ino)

### **Notes and Warnings**

# MP4Recording::getRecordingFileName

## **Description**

Get currently configured base file name of recording MP4 files.

## **Syntax**

String getRecordingFileName(void);

#### **Parameters**

NA

#### **Returns**

A String class object containing the currently configured MP4 base file name.

### **Example Code**

NA

## **Notes and Warnings**

# MP4Recording::getRecordingDuration

## **Description**

Get currently configured per-file MP4 recording duration.

## **Syntax**

uint32\_t getRecordingDuration(void);

#### **Parameters**

NA

#### **Returns**

Currently configured per-file recording duration, expressed in seconds.

## **Example Code**

NA

## **Notes and Warnings**

# MP4Recording::getRecordingFileCount

## **Description**

Get currently configured total number of MP4 files to record.

### **Syntax**

uint32\_t getRecordingFileCount(void);

#### **Parameters**

NA

#### **Returns**

Currently configured total number of MP4 files to record.

### **Example Code**

NA

## **Notes and Warnings**

# MP4Recording::getRecordingState

## **Description**

Get current MP4 recording state.

## **Syntax**

uint8\_t getRecordingState(void);

#### **Parameters**

NA

#### **Returns**

TRUE if MP4 is currently recording, FALSE if MP4 recording has stopped

## **Example Code**

NA

## **Notes and Warnings**

# MP4Recording::printlnfo

### **Description**

Print out current configuration of MP4 recording.

#### **Syntax**

void printlnfo(void);

#### **Parameters**

NA

#### **Returns**

NA

#### **Example Code**

Example: RecordMP4SingleVideoWithAudio

(https://github.com/ambiot/ambpro2\_arduino/blob/dev/Arduino\_package/hardware/libraries/Video/examples/RecordMP4SingleVideoWithAudio/RecordMP4SingleVideoWithAudio.ino)

## **Notes and Warnings**